

# Memory Allocation

## Computer Science 240

### Laboratory 12

In this lab, you will be introduced to the final project for the course, implementing a dynamic memory allocator for C programs.

The repository contains:

`Makefile` – recipes for compiling

`mdriver.c` – testing driver

`memlib.h` – memory/heap interface

`mm.c` – memory allocator implementation (**your code will go here**)

`mm.h` – memory allocator interface


`traces directory` – several trace files (`.rep`) used for simulated testing

the remaining files are testing support files you do not need to inspect

You will compile with `make` to produce an executable called `mdriver.bin`

There are a variety of ways to run the executable, described in the assignment (read carefully when you are ready to start testing your code).

## Block Structure



A **word** is 8 bytes in our machine.

The initial word of a block is called a **block header** or a **status word**, and stores the size of the block in bytes (multiple of 16).

It also stores whether the block is used, and whether the preceding block is used in the bottom two bits of the status word (called a **tag**).


The bottom two bits (**tags**) are:

Bit 1 ( $2^1 == 2$ ): PRED\_USED\_BIT [For coalescing]

Bit 0 ( $2^0 == 1$ ): USED\_BIT

Free blocks use the last word as a **footer**, which stores SIZE ONLY (no tags).

## Heap Block Layout (Implicit Free List)



## Heap Initialization in Starter Code

The starter code in `mm.c` gives you an `mm_init` function, which initializes the heap to a single **page** of memory, which is 4096 bytes, and contains a single large free block, along with the **heap header** and **heap footer**.

The heap header starts at an address which is word-aligned (boundary of 8). This guarantees that the first block payload also starts at a word-aligned address.

The heap footer is a special block of size 0 with the `USED_BIT` set to 1. This is the only block with this configuration, so marks the end of the heap.

The first block in the heap is assumed to always have the `PRED_USED_BIT` set to 1 (so that you will not try to coalesce memory below the heap when you free the first block).

## Memory Allocation in Starter Code

The starter code in *mm.c* also gives you a working memory allocation implementation, although it is **incomplete**.

Your job will be to write the code to complete it.

When an allocation occurs, the heap is checked to see if there is a large enough free block available for the allocation. If there is not a large enough block, the head is extended by a page which contains a large new free block.

When an allocation occurs, the heap is checked to see if there is a large enough free block available for the allocation.

If there is not a large enough block, the head is extended by a page which contains a large new free block.

The starter code does not split when you allocate, and it does not do anything when you free (it does not free the block, and does not coalesce as part of the free, either).

You will add code to the ***allocate*** function to implement splitting.

You will also write the ***mm\_free*** and ***coalesce*** functions.

## Traces

When learning about the starter code, you will simulate small **traces** (which are sequences of freeing and allocating blocks of various sizes). Results from the traces help you understand if your code is working correctly or not.

When testing and debugging, you may find it useful to write and test your own small traces.

A trace file contains 4 header lines:

- 1.Suggested heap size (any number, ignored by our tests).
- 2.Total number of blocks allocated.
- 3.Total number of malloc/free events.
- 4.Weight (any number, ignored by our tests).

Remaining lines after the header give a sequence of *memory management events* (either **free** or **allocate**), one per line.

For example, the following example C code would generate the corresponding trace below it.

C code:

```
p0 = malloc(12);  
p1 = malloc(16);  
p2 = malloc(16);  
free(p0);  
free(p1);  
p3 = malloc(24);
```

Corresponding trace:

```
128  
4  
6  
1  
a 0 12  
a 1 16  
a 2 16  
f 0  
f 1  
a 3 24
```

## Definitions in Starter Code

**Base address of the heap**

```
#define HEAP_BASE ((word_t*)mem_heap_lo())
```

**Bound address of the heap** (first address after the heap)

```
#define HEAP_BOUND ((word_t*)PADD(mem_heap_hi(), 1))
```

**Address of the heap header**

```
#define HEAP_HEADER_ADDR ((word_t**)HEAP_BASE)
```

**Address of the first block in the heap**

```
#define ORIGIN_BLOCK_ADDR ((word_t*)PADD(HEAP_BASE,  
WORD_SIZE))
```

**Address of the heap footer word**

```
#define HEAP_FOOTER_ADDR ((word_t*)PSUB(HEAP_BOUND,  
WORD_SIZE))
```

**Type for word**

```
typedef unsigned long word_t;
```

**Size of word** – pointers and **size\_t** values one word in size

```
#define WORD_SIZE (sizeof(word_t))
```

**Alignmnet** – Payloads must be aligned to 2 words

```
#define ALIGNMENT ((size_t)(2*WORD_SIZE))
```

**Minimum block size**

```
#define MIN_BLOCK_SIZE (ALIGNMENT)
```

## Functions for masking header/status word in Starter Code

The size and two tags can be extracted separately from the block header/status word by masking, using the following functions:

**status\_size(x)** extracts the block size information from a status word, x, masking off the other status bits

```
#define SIZE_MASK (~(ALIGNMENT - 1))
```

```
static word_t status_size(word_t status_word) {  
    return status_word & SIZE_MASK;  
}
```

**status\_pred(x)** extracts the predecessor status bit from a status word, x, masking off the other status bits

```
#define PRED_USED_BIT 2
```

```
static word_t status_pred(word_t status_word) {  
    return status_word & PRED_USED_BIT;  
}
```

**status\_used(x)** extracts the allocation status bit from a status word, x, masking off the other status bits

```
#define USED_BIT 1
```

```
static word_t status_used(word_t status_word) {  
    return status_word & USED_BIT;  
}
```



**make\_status(s,p,u)** makes a new status word by extracting the block size information from status word *s*, the predecessor status bit from word *p*, and the allocation status bit from word *u*.

WARNING: to set the predecessor or used bits explicitly, pass PRED\_USED\_BIT or USED\_BIT, not 1.

```
static word_t make_status(word_t size, word_t pred_used,
word_t used) {
    return (size & SIZE_MASK) |
           (pred_used & PRED_USED_BIT) |
           (used & USED_BIT);
}
```

### Functions for block headers in Starter Code

Provided for easy access/manipulation of block headers

**block\_get\_header(word\_t\* block)** gets header word of block

```
static word_t block_get_header(word_t* block) {
    return LOAD(block);
}
```

**block\_set\_header(word\_t\* block, word\_t header)** sets the header of the block

```
static void block_set_header(word_t* block, word_t header){
    STORE(block, header);
}
```

**block\_succ(word\_t\* block)** gets addr of block successor

```
static word_t* block_succ(word_t* block) {  
    // Get block's size from header and add to its address  
    return PADD(block, status_size(LOAD(block)));  
}
```

**block\_pred(word\_t\* block)** gets addr of block predecessor,  
assuming predecessor free

```
static word_t* block_pred(word_t* block) {  
    assert(!status_pred(LOAD(block))&&  
        "predecessor must be free");  
  
    // Get predecessor size from predecessor  
    footer and subtract from this block's address  
    word_t footer = LOAD(PSUB(block, WORD_SIZE));  
  
    // Footers must hold sizes  
    assert(status_size(footer) == footer &&  
        "footer must hold size only, no status bits");  
  
    return PSUB(block, footer);  
}
```

## Functions for unscaled pointer arithmetic (PADD and PSUM)

These functions are provided to help avoid pointer arithmetic mistakes

**PADD(void\* address, long distance)** perform unscaled pointer addition

```
static word_t* PADD(void* address, long distance) {  
    return ((word_t*)((char*)(address) + (distance)));  
}
```

**PSUB(void\* address, long distance)** perform unscaled pointer subtraction

```
static word_t* PSUB(void* address, long distance) {  
    return ((word_t*)((char*)(address) - (distance)));  
}
```

## Functions for pointer operations

The following functions can be used in place of pointer operations to help detect errors early and avoid casting and pointer noise. Verify that all pointers used, stored, and loaded point within the heap and are word-aligned

**LOAD(a)** loads a word from memory at address a

```
static word_t LOAD(word_t* address) {  
    assert(check_address(address) && "LOAD must load  
    from a 16-byte aligned address within the heap");  
    return *((word_t*)(address));  
}
```

**PLOAD(a)** loads a pointer word from memory at address a

```
static word_t* PLOAD(word_t** address) {
    assert(check_address(address) && "PLOAD must load
    from a 16-byte aligned address within the heap");

    word_t* ptr = *((word_t**)(address));

    assert(!ptr || check_address(ptr) && "PLOAD must
    return a 16-byte aligned address within the heap");

    return ptr;
}
```

**STORE(a,w)** stores word w into memory at address a

```
static void STORE(word_t* address, word_t word) {
    assert(check_address(address) && "STORE must store
    to a 16-byte aligned address within the heap");

    *((word_t*)address) = word;
}
```

**PSTORE(a,w)** stores pointer word w into memory at address a

```
static void PSTORE(word_t** address, void* ptr) {
    assert(!ptr || check_address(ptr) && "PSTORE
    must store a 16-byte aligned address within the heap");

    assert(check_address(address) && "PSTORE must store to a
    16-byte aligned address within the heap");

    *((word_t**)address) = ptr;
}
```